

# Accessing and Transferring Onboard Code from Unitree Go2

The Unitree Go2 communicates over a private Ethernet network (192.168.123.18). Since the robot does not always provide DHCP, a static IPv4 configuration is required on the host machine.

1. Connect the laptop to the Go2 using a USB-Ethernet or Ethernet cable. Connect yellow ethernet cable to RJ45 jack and other end to laptop/hub via USB-C cable
2. Configure a static IPv4 address on the host laptop:  
Steps for windows -> settings -> network & internet -> ethernet -> change IP assignment to manual and add below IPv4 details
3. IP address: 192.168.123.100
4. Subnet mask: 255.255.255.0
5. Go to powershell and type `ipconfig` and see if above ip address is visible in IPv4
6. If yes, Verify connectivity using `ping 192.168.123.18`
7. 4 pings will be transferred and returned with no loss.

```
Pinging 192.168.123.18 with 32 bytes of data:
Reply from 192.168.123.18: bytes=32 time=5ms TTL=64
Reply from 192.168.123.18: bytes=32 time=2ms TTL=64
Reply from 192.168.123.18: bytes=32 time=1ms TTL=64
Reply from 192.168.123.18: bytes=32 time=2ms TTL=64

Ping statistics for 192.168.123.18:
    Packets: Sent = 4, Received = 4, Lost = 0 (0% loss),
    Approximate round trip times in milli-seconds:
        Minimum = 1ms, Maximum = 5ms, Average = 2ms
```

1. Once network connectivity is confirmed, access the robot using SSH. This provides terminal access to the onboard Ubuntu environment running on the Go2. `ssh unitree@192.168.123.18`
2. Password: 123
3. Upon successful connection you should see an option to choose between ROS foxy or noetic. Choose 1 to use ROS foxy

```
ros:foxy(1) noetic(2) ?
1
```

Use `ls` command to view all files and folders onboard.

```
-bash: /home/unitree/cyclonedds_ws/install/setup.bash: No such file or directory
unitree@ubuntu:~$ ls
acll_offline_files      Documents          Public
camera_calibration      Downloads         robot_continous.py
camera_calibration.txt  export.py         robot_movement_server.py
captured_images        go2_ball_follower.py  Templates
cuda-keyring_1.1-1_all.deb  go2_webrtc_connect  test_cuda
cudnn_install          move_debug.py      test_cuda.cu
cyclen_diagnise.sh      movement_tester.py  torch-2.1.0a0+41361538.nv23.06-cp38-cp38-linux_aarch64.whl
cyclonedds             Music             torchvision_build
dataset_server.py       nomachine.sh      unitree_webrtc_connect
depth_test             Pictures          Videos
Desktop               yolov8n.pt
unitree@ubuntu:~$ cd depth_test
unitree@ubuntu:~/depth_test$ ls
ball_follow_pose.py      gdb.txt           velocities.txt    yolov8s.pt       yolov8s_test_5.jpg
file_control.log         pose_control.py  voice_agent      yolov8s_test_0.jpg yolov8s_test_6.jpg
file_control.py          target.txt       yolo_debug.py   yolov8s_test_1.jpg yolov8s_test_7.jpg
file_control.py.bak      test_coloured_model.py  yolo_models.py  yolov8s_test_2.jpg yolov8s_test_8.jpg
final_ball_identification.ipynb  test_yolov8n.py  yolov8n.onnx    yolov8s_test_3.jpg yolov8s_test_9.jpg
final_best.pt            test_yolov8n.py.bak  yolov8s.onnx    yolov8s_test_4.jpg
```

- Files related to robot perception and movement are saved in the `depth_test` folder.
- Run the files `test_coloured_model.py` and `file_control.py` in two separate terminals to make the robot move by itself and detect multi-colored balls.
- `Final_best.pt` model is used by `test_coloured_model.py` file
- To view the robot camera, access the `laptop_viewer.py` file via another terminal through this code command  
`python <file path> <ip:default value 192.168.123.18>`

## Best Practices

- Avoid modifying onboard robot code directly
- Always develop and test locally before deploying changes back to the robot.
- Transfer only required source files (scripts, models, configs) to keep workflows clean and reproducible.
- Maintain backups before experimentation

## Helpful Links

- Github Repo: [Link](#)
- Video demonstration: [Link 1](#) , [Link 2](#)
- Poster: [Link](#)